

Hygge Heart Cushion Cover





Hygge Heart Cushion Cover Materials

UK terminology

2 balls Stylecraft Bellissima - Single Cream (acrylic dk)

1 ball Wendy Aurora - Electrons (acrylic self-stripping dk - this yarn is a very thick dk)

4.5 mm hook

3 x 1.5 cm diameter heart buttons

Tapestry needle and sharp scissors

Cushion insert 16 inch x 16 inch (approx 41 x 41 cm)

It is possible to use other yarn types, however, the sizes of the finished article may be altered and the yarn quantities may be different.

Tension and sizing

14 stitches x 20 rows over 10 cm².

The cushion cover will fit a 16 x 16 (approx. 41 cm x 41 cm) inch cushion. Do not worry when crocheting if the material appears smaller, as there is room for expansion when finished to this tension. It will expand on blocking and when the cushion insert is placed inside it.





Hygge Heart Cushion Cover *Pattern Notes - UK Terminology*

UK terminology

This pattern is worked in rows using the intarsia method working backwards and forwards with the yarn held/carried on the wrong side. If you are new to intarsia, I have a handy guide on [my blog](https://www.crochetcloudberry.co.uk/blog). ([crochetcloudberry.co.uk](https://www.crochetcloudberry.co.uk))

When working with cream/white yarn, I would recommend not carrying the yarn through the stitches, but simply holding it behind the crochet, as in the photo below. Otherwise the pink may show through the cream.



Once you have crocheted your foundation chain, the pattern starts in the bottom right corner of each chart. That means that you are working right to left, bottom to top.

Each square represents 1 dc apart from rows 6, 25, 44 and 63 on the front, row on 9 on 1st back piece and row 37 on 2nd back piece (these rows are explained in the pattern).

At the end of each row chain 1 to turn, this chain is not counted as a stitch.

Each time you join a new colour, e.g., for the stripes, hold the material with the front side facing you and join the yarn from the right hand side. Make sure you do this, even when you are working a row that would normally be a return row; in that case fasten off the yarn and restart with the new colour from the right hand side with the front facing you. This way of working ensures that the stripes and hearts have a consistent and neat appearance.

Copyright held by Catherine Venner of [Crochet Cloudberry](https://www.crochetcloudberry.co.uk). Please do not copy, resell or redistribute this pattern. Please feel free to crochet small quantities of this cushion cover for sale, however, where possible refer and link to Crochet Cloudberry as the designer.



Hygge Heart Cushion Cover Front

UK terminology

Foundation row: With cream chain 58.

1st row: Dc into second chain from hook. Dc across. (57)

Rows 2 to 68: Continue to follow the chart using the intarsia method starting at the bottom right corner. Please make colour changes according to the chart. Pay attention to the special instructions for rows 6, 25, 44 and 63.

Rows 6, 25, 44 and 63: These rows are made up of two rows of stitches but for the purposes of this pattern count as one row.

Start from right hand side when holding work with the front facing you. Join pink as dc in the second stitch from right end, then *chain 1, miss 1, 1 dc. Repeat from * to end. The final dc in pink should be in the second from last stitch in the row. Fasten off.


With cream, starting from right hand side when holding work with right side facing you. 1 dc in the first stitch of the row below (i.e., into row 5, 24, 43 and 62), *chain 1, miss 1 (the one you miss is the dc in pink), then dc into the row below (i.e., row 5, 24, 43 and 62). To do this you are crocheting the dc over the chain 1 in pink. Repeat from* to end. The final stitch should be a dc. 1 chain to turn, and then work the return rows (rows 7, 26, 45 and 64) according to the chart with 1 dc in each stitch and chain-1-space. Follow the rest of the pattern according to the chart.

Tip: When changing colours, it is easy to lose or gain stitches, so count the stitches at the end of each row to ensure you have 57 stitches.

Tip: You may want to have a looser tension than normal to ensure the stitches before and after the colour change do not get lost by being pulled too tightly into the material.



Hygge Heart Cushion Cover *UK terminology*
Hygge Heart Cushion Cover - Front Chart



Pink
 Cream

Copyright held by Catherine Venner of [Crochet Cloudberry](http://CrochetCloudberry.com). Please do not copy, resell or redistribute this pattern. Please feel free to crochet small quantities of this cushion cover for sale, however, where possible refer and link to Crochet Cloudberry as the designer.



Hygge Heart Cushion Cover

Back

UK terminology

The back is made up of two pieces. Both pieces are crocheted in rows using simple dc apart from row 9 on the 1st back piece and row 37 on the 2nd back piece.

1st Back Piece

Please make colour changes according to the chart. A grey square indicates that the stitch is to be missed. Remember to chain 1 at the end of each row to turn.

Foundation row: With cream chain 58.

Row 1: 1 dc into second chain from hook. Dc across. (57)

Rows 2 to 43: Continue to follow the chart where each square represents 1 dc apart from on row 8, which is made up of two rows of stitches but for the purposes of this pattern count as one row. Please make colour changes according to the chart.

Row 8: Start from right hand side when holding work with the front facing you. Join pink as dc in the second stitch from right end, then *chain 1, miss 1, 1 dc. Repeat from * to end. The final dc in pink should be in the second from last stitch in the row. Fasten off.

With cream starting from right hand side when holding work with right side facing you. 1 dc in the first stitch of the row below (i.e., row 7), *chain 1, miss 1 (the one you miss is the dc in pink), then dc into the row below (i.e., row 7). To do this you are crocheting the dc over the 1 chain in pink. Repeat from* to end. The final stitch should be a dc. 1 chain to turn, and then work the return row 9 on the wrong side according to the chart with 1 dc in each stitch and chain-1-space. Follow the rest of the pattern according to the chart.




Hygge Heart Cushion Cover Trim

UK terminology

Row 44: Using pink 1 dc in first stitch, *chain 1, miss 1, 1 dc. Repeat from * to end.

1st Back Piece Chart



2nd Back Piece (With Buttonholes)

Please make colour changes according to the chart. A grey square indicates that the stitch is to be missed Remember to chain 1 at the end of each row to turn.

Foundation row: With cream chain 58.

Row 2 (You start this piece on row 2 because row 1 in the chart is worked once the rest of the piece is completed): dc into second chain from hook. Dc across. (57)

Row 3 and 4: Dc across.





Hygge Heart Cushion Cover *Buttonholes*

UK terminology

Row 5: 13 Dc, chain 2, miss 2, 12 dc, chain 2, miss 2, 12 dc, chain 2, miss 2, 14 dc, turn.

Row 6: 13 dc, 2 dc in chain-2-space, 12 dc, 2 dc in chain-2-space, 12 dc, 2 dc in next chain-2-space, 14 dc, turn.

Rows 6 to 43: Dc across. Follow the chart where each square represents 1 dc apart from on row 37.

Row 37: Start from right hand side when holding work with the front facing you. Join pink as dc in the second stitch from right end, then *chain 1, miss 1, 1 dc. Repeat from * to end. The final dc in pink should be in the second from last stitch in the row. Fasten off.

With cream starting from right hand side when holding work with right side facing you. 1 dc in the first stitch of the row below (row 36), *chain 1, miss 1 (the one you miss is the dc in pink), then dc into the row below (row 36). To do this you are crocheting the dc over the 1 chain in pink. Repeat from* to end. The final stitch should be a dc. 1 chain to turn, and then work the return row 38 on the wrong side according to the chart with 1 dc in each stitch and chain-1-space. Follow the rest of the pattern according to the chart and fasten off.


Trim

Turn piece upside down so that you are working into the foundation chains. Hold right side facing you. Using pink 1 dc in first stitch, *chain 1, miss 1, 1 dc. Repeat from * to end. Fasten off.



Hygge Heart Cushion Cover 2nd Back Piece Chart

UK terminology





Hygge Heart Cushion Cover Making Up

UK terminology

Weave in all ends and block all three pieces.

Start with back piece 1 and the front of cushion cover. Position the pieces together at the bottom of the front (so that you will crochet the piece together into the foundation rows) and with the right sides facing. Use dc at regular intervals along the sides to attach the pieces together. Turn inside out so that the wrong sides are now facing each other and the right sides are facing out. Fasten off.

With back piece 2 and front, position pieces at the top of the front and with right sides facing. There should be some overlap with back piece 1 in the middle. Use dc along the sides to attach the pieces together. Turn so that the wrong sides are now facing. Fasten off. The piece should now form an envelope opening.

Trim

Working on the right side, you should be able to see the dcs that you used to attach the front to back pieces. Use pink to dc into these stitches at regular intervals around the cushion.

Attach buttons

Now insert the cushion and position the buttons so that they will go through the buttonholes.



Congratulations, you have now made the Hygge Heart Cushion Cover. I hope that you enjoyed the pattern. If you have any questions, please contact me at: cat@crochetcloudberry.co.uk and state the name of this pattern in the email heading.

I would love to see your finished Hygge Heart Cushion Cover, so if you would like to share please:

tag me on [Instagram](#)

Link your finished cushion cover to my [ravelry page](#)

Share on [Facebook](#)

Follow Crochet Cloudberry on [Pinterest](#)

Or use the hashtags [#crochetcloudberry](#) and [#hyggeheartcushion](#)